



Proxmox Monitoring Influxhdb2 and Grafana


Add new metric server on proxmox, generate token from InfluxDB, make sure you get read/write access token API.

Make sure bucket and name patch, we are using organization htf and http port 8086







Create new API this time for grafana and give all read access to all buckets



On grafana we will add a new source where URL IP is our Influxdb



Save and test should work next we will add a new dashboard, we are using <https://grafana.com/grafana/dashboards/17051-proxmox/?tab=revisions> for our dashboard, copy code and import to grafana

Import dashboard

Import dashboard from file or Grafana.com



Upload dashboard JSON file

Drag and drop here or click to browse

Accepted file types: .json, .txt

Find and import dashboards for common applications at grafana.com/dashboards

Load

Import via dashboard JSON model

```
{
  "title": "Example - Repeating Dictionary variables",
  "uid": "_0HnEoN4z",
  "panels": [...]
  ...
}
```

Load

Cancel

Select DB (Influxdb) give it a name and import

Import dashboard

Import dashboard from file or Grafana.com

Importing dashboard from Grafana.com

Published by

blithe.dev

Updated on

2022-09-26 08:14:01

Options

Name

Proxmox Influx 2.0 Dashboard

Folder

Dashboards

Unique identifier (UID)

The unique identifier (UID) of a dashboard can be used to uniquely identify a dashboard between multiple Grafana installs. The UID allows having consistent URLs for accessing dashboards so changing the title of a dashboard will not break any bookmarked links to that dashboard.

lfgdXjtns


Change uid

InfluxDB

influxdb

Import

Cancel



you can use the following command on Proxmox to view influxdb errors

```
journalctl -a | grep influxdb
```

Also if no data is being sent make sure pvestatd is running on proxmox

```
root@pve:~# pvestatd status
running
root@pve:~# pvestatd
help      restart  start    status   stop
```

Revision #2

Created 21 May 2024 05:48:02 by Cesar Gzz

Updated 21 May 2024 16:06:04 by Cesar Gzz